



ControlNet Interface Module 1784-PCIC/S

Use These Release Notes

Use these release notes with publication 1784-IN003A-EN-P, ControlNet Interface Module Installation Instructions, published October 2000.

Compatible RSLinx Releases

RSLinx 2.2 Service Pack 2 (2.20.02 Build 26) or later is compatible with release 3.5 of the 1784-PCIC/S firmware.

RSLinx 2.3 (2.30.01 Build 48) or later is **required** for Windows 98. RSLinx 2.3 (2.30.01 Build 48) or later is **recommended** for Windows NT 4.0 and Windows 2000.

Visit the Rockwell Automation Software Updates web page at <http://support.automation.rockwell.com/webupdates/> to download an update for RSLinx.

Compatible RSNetWorx Releases

If you want to schedule a ControlNet network via the 1784-PCIC/S card, RSNetWorx for ControlNet 3.0 SP1 (3.00.01 Build 11) or later is **required**.

Visit the Rockwell Automation Software Updates web page at <http://support.automation.rockwell.com/webupdates/> to download an update for RSNetWorx.


Corrected Anomalies

These anomalies have been corrected for the 1784-PCIC/S in release 3.5 of the firmware and release 3.1 of the driver. Release 3.1 of the 1784-PCIC/S driver is included with RSLinx 2.3 (2.30.01 Build 48) or later.

- Operations using RSLinx are less likely to time out. These operations include browsing to a remote DH+ network with RSWho and uploading/downloading with RSLogix Programming Software.
- The driver now properly supports Windows 98.
- The driver now rejects system requests to enter lower power states since the 1784-PCIC/S hardware does not support stand-by mode.
- Shutting down Windows 2000 no longer causes the host PC to lock up or blue screen when the 1784-PCIC/S card is sharing interrupts.
- The 1784-PCICS card now supports multicast scheduled I/O from ControlNet to multiple slots in the Virtual Backplane. This means that multiple SoftLogix 5800 processors can receive the same I/O data produced by a single node on ControlNet.
- The 1784-PCICS card now supports multicast scheduled I/O from one 1784-PCICS card to multiple connection originators. This means that multiple connection originators can read the same SoftLogix 5800 produced tag through the 1784-PCICS card.
- RSLogix 5000 Programming Software can now be used to reset the 1784-PCICS card.

Known Anomaly

When going online with RSNetWorx for ControlNet software via the 1784-PCIC/S card, select 'Port A, ControlNet' under the card in the Virtual Chassis. Do **not** select 'AB-PCIC-1, ControlNet'.



If the Virtual Backplane driver is not available, follow these steps to set up the Virtual Backplane driver in RSLinx:

1. Select Communications -> Configure Drivers...
2. Under Available Driver Types, select 'Virtual Backplane (SoftLogix 58xx)'.
3. Press Add New.
4. Enter a name for the driver and press OK.
5. Press Close. The Virtual Backplane driver is now available to use.

RSNetWorx and RSLinx are trademarks of Rockwell Software.

ControlNet is a trademark of ControlNet International.

Reach us now at www.rockwellautomation.com

Wherever you need us, Rockwell Automation brings together leading brands in industrial automation including Allen-Bradley controls, Reliance Electric power transmission products, Dodge mechanical power transmission components, and Rockwell Software. Rockwell Automation's unique, flexible approach to helping customers achieve a competitive advantage is supported by thousands of authorized partners, distributors and system integrators around the world.

Americas Headquarters, 1201 South Second Street, Milwaukee, WI 53204, USA, Tel: (1) 414 382-2000, Fax: (1) 414 382-4444
European Headquarters SA/NV, avenue Hermann Diebroux, 46, 1160 Brussels, Belgium, Tel: (32) 2 663 06 00, Fax: (32) 2 663 06 40
Asia Pacific Headquarters, 27/F Citicorp Centre, 18 Whitfield Road, Causeway Bay, Hong Kong, Tel: (852) 2887 4788, Fax: (852) 2508 1846



Publication 1784-RN530A-EN-P - July 2001

PN 957564-57

© 2001 Rockwell Automation. Printed in the U.S.A.